



CHDK and CHDK GPS Settings:




Shutter Speed / General
* uncheck 'Clear override values@start'




CHDK GPS Settings



CHDK GPS Settings
* update 'Sampling interval until' setting



Intervalometer Script
* update Autostart and settings. -100 = zoomed out lens



Intervalometer Script



CHDK GPS Settings

Canon Settings:



Canon GPS Settings



Flash Settings



Image Stabilization Settings



Time Settings
* update 'GPS Auto Time'



General Canon Settings



General Canon Settings



General Canon Settings



General Canon Settings



General Canon Settings



General Canon Settings

Example Images:



Falcon UAV Example Imagery from Canon SX260HS at 200 meters. 6.7 Ground Sample Distance (GSD)